


Android Pull Mail 設定


在未進行 Pull Mail 在手提電話設定前，請先行確定閣下之手提電話有上網功能。請開啓 Browser 軟件來試行上網。於網址列輸入 <http://www.google.com.hk> 嘗試瀏覽網頁。如成功瀏覽網頁，可以繼續下一步驟。

如未能成功瀏覽網頁，請聯絡閣下電話供應商之技術支援。



(figure 1)


如能通過上網測試，請開啓 email 軟件。




請按次序輸入閣下的資料

1. email address : 輸入你的電郵地址, 例如 peter.ch.chan@midland.com.hk
2. password : 輸入你的電郵密碼
3. 然後按「next」。

如閣下不清楚應輸入的資料，可與資訊科技部聯絡 (電話：2273 6666)



請選擇「IMAP」。



Incoming Server Settings.

請輸入以下資料

1. Username : 例如 : peter.ch.chan
2. Password : 輸入你的電郵密碼
3. IMAP Server 請輸入以下資料:
 - A. 香港區同事請輸入
mail1.midland.com.hk
 - B. 九龍區同事請輸入
mail2.midland.com.hk
 - C. 新界區同事請輸入
mail3.midland.com.hk
4. Port 請輸入 143
5. 然後按「next」



The screenshot shows the 'Incoming server settings' screen. It has a dark background with white text and input fields. The fields are: Username (with a red box around it), Password (with dots), POP3 server, Port, Security type (set to None), and Delete email from server (set to Never). At the bottom right, there is a 'Next' button with a green arrow, which is circled in red.

Outgoing Server Settings

請輸入以下資料

1. SMTP Server 請輸入
 - A. 香港區同事請輸入
mail1.midland.com.hk
 - B. 九龍區同事請輸入
mail2.midland.com.hk
 - C. 新界區同事請輸入
mail3.midland.com.hk
2. Port 請輸入 25
3. Username : 輸入你的電郵用戶,
例如: peter.ch.chan
4. Password : 輸入你的電郵密碼
5. 然後按「next」




The screenshot shows the 'Outgoing server settings' screen. It has a dark background with white text and input fields. The fields are: SMTP server (with a red box around it), Port, Security type (set to None), a checked 'Require sign-in' checkbox, Username, and Password (with dots). At the bottom right, there is a 'Next' button with a green arrow, which is circled in red.

1. 請確定已選擇 Notify me when email arrives.
2. 然後按「next」



然後按「DONE」



如有任何查詢，閣下可以與資訊科技部聯絡

電話： 2273 6666